



Step-1

首先啟動 Windows Live Mail，開啟後請至上方工具列中選取【帳戶】選項。



Step-2

開啟【帳戶】選項後，點選【電子郵件】。



Step-3

點選後，請填寫所要新增郵件帳號的資料欄位，並請勾選【手動設定伺服器設定】。

A screenshot of the '新增電子郵件帳戶' (Add New Email Account) dialog box. The title is in green. The form contains the following fields and options:

- '電子郵件地址:' (Email address): A text box with the placeholder '輸入您的信箱完整地址' (Enter your complete mailbox address) in red. Below it is a link: '取得 Windows Live 電子郵件地址' (Get Windows Live email address).
- '密碼:' (Password): A text box with four dots. Below it is a checked checkbox: '記住此密碼(B)' (Remember this password).
- '您傳送郵件的顯示名稱:' (Display name for outgoing mail): An empty text box.
- Below the display name field are two checked checkboxes:
 - '將此帳戶設為預設電子郵件帳戶(D)' (Set this account as the default email account).
 - '手動設定伺服器設定(C)' (Manually configure server settings).

On the right side of the dialog, there is explanatory text: '大多數電子郵件帳戶皆可使用 Windows Live Mail 郵件軟體，包括 Hotmail、Gmail 以及其他服務。' (Most email accounts can be used with Windows Live Mail software, including Hotmail, Gmail, and other services). At the bottom right, there are two buttons: '取消' (Cancel) and '下一步' (Next).

Step-4

選擇使用的 POP3 伺服器類型以及伺服器位址，並請勾選【需要驗證】。

Step-5

設定完成後，請測試 E-Mail 是否能正常收發信件。

請登入新版 Webmail <https://triton.url.com.tw/rcmail/> 查詢收件伺服器設定值
及寄件伺服器設定值

智邦生活館
Webmail 2.0

設定 資料夾 簽名檔 1

分類
使用介面設定
信箱顯示設定
撰寫郵件設定
郵件顯示設定
通訊錄
行事曆
郵件編輯器設定
設定簡訊/傳真帳號
預約郵件/延遲寄信
別名信箱
設定郵件轉寄
設定自動回覆
使用者密碼
外部 POP3 信箱
郵件過濾器
設定防堵等級
垃圾信箱白名單
傳真信箱
登入記錄
IMAP/POP3/SMTP 服務設定
兩階段身份驗證
郵件 Line 通知
Outlook 外掛設定

企業信箱設定說明：

- OutLook Express 設定方式
- OutLook 2010 設定 **3**
- MozillaThunderbird 設定
- iOS 系統行動裝置(Ipad / iPhone)信箱設定
- Android 系統行動裝置(SAMSUNG / HTC / SONY.....)信箱設定

OutLook 2010 設定	
SSL/TLS 設定 (推薦)	
伺服器設定	內送郵件伺服器 pollux6.url.com.tw 4 需要安全資料傳輸層 (SSL) : 是 IMAP 連接埠 : 993 POP3 連接埠 : 995
	外寄郵件伺服器 pollux6.url.com.tw 5 需要安全資料傳輸層 (SSL) : 是 SMTP 連接埠 : 465或587
登入資訊	使用者名稱 bbtest123@linuxdemo.url.tw
	密碼 *****

詳細說明請連到 [OutLook 2010 設定](#)