



Step-1

首先啟動 Windows Live Mail，開啟後請至上方工具列中選取【帳戶】選項。



Step-2

開啟【帳戶】選項後，點選【電子郵件】。



Step-3

點選後，請填寫所要新增郵件帳號的資料欄位，並請勾選【手動設定伺服器設定】。

A screenshot of the "新增電子郵件帳戶" (Add New Email Account) wizard screen. The title is "新增電子郵件帳戶". The screen contains several input fields and checkboxes:

- "電子郵件地址:" (Email address): A text box with the placeholder "輸入您的信箱完整地址" (Enter your complete mailbox address) and a link "取得 Windows Live 電子郵件地址" (Get Windows Live email address).
- "密碼:" (Password): A text box with "...." and a checked checkbox "記住此密碼(B)" (Remember this password).
- "您傳送郵件的顯示名稱:" (Display name for outgoing mail): A text box.
- Two checked checkboxes at the bottom: "將此帳戶設為預設電子郵件帳戶(D)" (Set this account as the default email account) and "手動設定伺服器設定(C)" (Manually configure server settings).

On the right side, there is explanatory text: "大多數電子郵件帳戶皆可使用 Windows Live Mail 郵件軟體，包括 Hotmail、Gmail 以及其他服務。" (Most email accounts can use Windows Live Mail email software, including Hotmail, Gmail, and other services). At the bottom right, there are two buttons: "取消" (Cancel) and "下一步" (Next Step).

Step-4

選擇使用的 POP3 伺服器類型以及伺服器位址，並請勾選【需要驗證】。

Step-5

設定完成後，請測試 E-Mail 是否能正常收發信件。

請登入新版 Webmail <https://triton.url.com.tw/rcmail/> 查詢收件伺服器設定值
及寄件伺服器設定值

智邦生活館
Webmail 2.0

1. Outlook Express 設定方式
3. 2. Outlook 2010 設定

Outlook 2010 設定	
SSL/TLS 設定 (推薦)	
伺服器設定	內建郵件伺服器
	pollux9.url.com.tw 需要安全資料傳輸層 (SSL) : 是 IMAP 連接埠 : 993 POP3 連接埠 : 995
外寄郵件伺服器	pollux9.url.com.tw 需要安全資料傳輸層 (SSL) : 是 SMTP 連接埠 : 465 或 587
	登入資訊
	使用者名稱: test@teaching.url.tw 密碼: * * * * *
非 SSL 設定 (不建議)	
伺服器設定	內建郵件伺服器
	pollux9.url.com.tw 需要安全資料傳輸層 (SSL) : 否 IMAP 連接埠 : 143 POP3 連接埠 : 110
外寄郵件伺服器	pollux9.url.com.tw 需要安全資料傳輸層 (SSL) : 否 SMTP 連接埠 : 25
	登入資訊
	使用者名稱: test@teaching.url.tw 密碼: * * * * *

2. IMAP/POP3/SMTP 服務設定